

Linking mailf.piac.aero to iOS (Apple Devices)

NOTE : Follow the initial steps mentioned in the Circular to assign your own password as the one stated in the Circular is only **Temporary** & cannot be used to link to an application.

THIS GUIDE IS ONLY FOR iOS (APPLE DEVICES)

Date:4/17/2026

Time:3:27 PM

FLT OPS / TECH / 171/Apr 17, 2026

To :
B777
A320
ATR

Subject : OFFICIAL EMAIL ADDRESS

PIA is in the process of assigning official email accounts to all crew members. You may access detailed instructions by selecting the relevant tabs for Android and iOS devices.

Each crew member's email address will follow a standardized format: your Personnel Number followed by @piac.aero. For example, if your P No is 30694, your email address will be 30694@piac.aero. A one-time password will be 1234\$mal@

You may access your email directly via the web at:

<https://mailf.piac.aero>

OPTION 1:

Settings for MAIL for iOS Apple Devices




1. Go to 'Settings'



Settings


2. Then select or search for the 'MAIL' Application




3. Go to 'Mail Accounts'




4. Go to 'Add Account'




5. Enter your email address e.g(64536@piac.aero)




6. Select (Add Other Account) when popup comes for 'Choose your provider'



7. Select 'Mail Account'




8. Fill the required fields as stated example below



The screenshot shows a 'New Account' form with the following fields and values:

Field	Value
Name	Faizan Junaid
Email	64536@piac.aero
Password	
Description	PIA Official ID

9. Make sure 'IMAP' is selected



The screenshot shows the 'New Account' form with two radio button options: 'IMAP' and 'POP'. A red arrow points to the 'IMAP' option, indicating it should be selected.

10. Fill the fields according to the example stated below

Name	Faizan Junaid
Email	64536@piac.aero
Description	PIA Official ID

Incoming Mail Server

Host Name	mailf.piac.aero	←
User Name	64536@piac.aero	←
Password		←

Outgoing Mail Server


Host Name	mailf.piac.aero	←
User Name	64536@piac.aero	←
Password		←

OPTION 2 :


Settings for **GMAIL**




1. Install 'GMAIL' from the App Store if previously not installed




2. Click the User Icon




3. Select 'Add another Account'



4. Select 'Other (IMAP)'




5. Fill the required fields as stated below



The screenshot shows an email account setup interface. At the top, there are three navigation options: a back arrow labeled "Add account", the title "Add account", and a "Next" button. Below the navigation is the Gmail logo. The main heading is "Add your email address". There is a radio button option labeled "Other (IMAP)". Below this is a text input field for the "Email address". The field contains the text "64536@piac.aero". A large red arrow points from the right side of the field towards the text, highlighting the input.

[Add account](#) **Add account** [Next](#)




Add your email address

Other (IMAP)


Email address

64536@piac.aero

6. Incoming Server Settings



[Add account](#) **Add account** [Next](#)



Incoming server settings

Username
64536@piac.aero

Password


IMAP server
mailf.piac.aero

Port
993


Security type
SSL/TLS

Detailed description: This is a screenshot of the 'Incoming server settings' screen in an email client. At the top, there are three navigation links: a back arrow, 'Add account', and 'Next'. Below the Gmail logo, the title 'Incoming server settings' is displayed. The form contains five fields, each with a red arrow pointing to its content: 'Username' with '64536@piac.aero', 'Password' (empty), 'IMAP server' with 'mailf.piac.aero', 'Port' with '993', and 'Security type' with a dropdown menu showing 'SSL/TLS'.

7. Outgoing Server Settings



[Add account](#) **Add account** [Next](#)



Outgoing server settings

Username
64536@piac.aero

Password


SMTP server
mailf.piac.aero

Port
587

Security type
STARTTLS

Detailed description: This is a screenshot of the 'Outgoing server settings' screen in an email client. At the top, there are three navigation links: a back arrow, 'Add account', and 'Next'. Below the Gmail logo, the title 'Outgoing server settings' is displayed. The form contains five fields, each with a red arrow pointing to its content: 'Username' with '64536@piac.aero', 'Password' (empty), 'SMTP server' with 'mailf.piac.aero', 'Port' with '587', and 'Security type' with a dropdown menu showing 'STARTTLS'.

8. Once setup is complete, the following msg will appear



STEP BY STEP PROCESS FOR APPLE MAIL

- 1) Go to settings
- 2) Open mail or search for it
- 3) Go to **accounts**
- 4) Tap **add account**
- 5) Select **other** when the provider list appears
- 6) Tap **add mail account**
- 7) Enter name, email e.g. (**12345@piac.aero**), **password** and add a description like **PIA Official id**
- 8) Make sure “**imap**” Tab is selected
- 9) Under incoming mail server
 - Host name **mailf.piac.aero**
 - **Username** full email address
 - Password your **password**
- 10) Under outgoing mail server
 - Host name **mailf.piac.aero**
 - Username, full email address (**P.No**)@piac.aero
 - Password, your **password**